

Predictive Project Quick User Guide

May 16, 2011



Preface

This product guide is divided into chapters; each chapter describes a specific topic. Certain typographical conventions are used throughout this product guide. See below:

- All commands you enter via keystrokes appear in bold (e.g., Press Enter or Press Ctrl-I).
- All text commands you enter into text boxes or other command line typing appear in italics (e.g., type *active*).
- All pull down menu options, figure references, and table references appear in italics in the menu order to select (i.e., Choose *File> Open*).
- There are three types of special text that are designed to reveal supplemental information: Note, Warning, and Caution. See below.



A **NOTE** provides additional, helpful information. This information may tell you how to do a certain task or just be a reminder for how-to's given in previous sections



A **WARNING** provides information about how to avoid harm to your system (i.e., do not delete your company).



A **CAUTION** provides information about how to avoid malfunction or unwanted Results (i.e., When using the IN logic always separate text with a single quote).

Preface Page i


Table of Contents

Preface	
TABLE OF CONTENTS	II
CHAPTER 1: BUSINESS TO BUSINESS DIALING	3
SEND ANI	3
VOICE CHANNELS, AND PLAY NOTIFICATION BEEP TO AGENT	
RINGTIME AND TONE DETECTION	
MAXIMUM DROPPED CALL RATE AND AGGRESSIVITY FACTORS	
CHAPTER 2: BUSINESS TO CONSUMER DIALING	
SEND ANI	6
VOICE CHANNELS, AND PLAY NOTIFICATION BEEP TO AGENT	
RINGTIME AND TONE DETECTION	
MAXIMUM DROPPED CALL RATE AND AGGRESSIVITY FACTORS	
ACTIONS	8
CHAPTER 3: DIALER LISTS	9
TIME ZONES	12
CCA REPORTS	
LIST ACTIVATION	15
CONTACT AND SUPPORT INFORMATION	16
Sales and Product Information	16
Technical Support	

Chapter 1: Business to Business Dialing

Send ANI

It is important to send a valid caller id (ANI) when dialing to enable the persons being dialed to return your call. On the general tab of the project to be dialed is the setting to allow this; a dropdown labeled Outbound ANI/CLI:




Voice Channels, and Play Notification Beep to agent

On the predictive tab is the Maximum Number of Voice Channels to be used and the Play notification beep to agent setting, check so that agents hear a short beep when they connect to a predictive call. The Maximum Number of Voice Channels should be set to 1.5 times the number of agents logged in. Number of Retry should be set to between 5 and 10 (based on your specific needs)




(Note: The number of times a callback contact record is called is based on specific campaign requirements this suggested value is a typical setting used by most user)



Ringtime and tone detection


The ringtime setting on the regulations tab specifies how long, in seconds, the system will let a call ring before determining it as no answer, for Business to Business dialing, 30 seconds of ringtime is optimal,

From the Tone Detection drop-down list, select how long CCA waits (in seconds) to determine whether the call was answered by a person or an answering machine. (CCA determines this by running an algorithm.) For Business to Business dialing 0.5 seconds is optimal



Maximum Dropped Call Rate and Aggressivity Factors

Type the maximum percentage of dropped predictive calls to allow in the Maximum Dropped Call Rate field, this should be set to 3.0, and the Aggressivity factors should remain at the default setting, and the Sampling size should be set to 300




Actions

For each condition (If Busy, If No Answer, and so on) select an action for CCA to take. (Notice that new fields appear after making a selection.)

If Answering Machine -> Connect agent




(Note: This is based on campaign needs however, this is a typical setting to ensure IVR and automated attendants can be navigated by the user)



Chapter 2: Business to Consumer Dialing

Send ANI

It is important to send a valid caller id (ANI) when dialing to enable the persons being dialed to return your call. On the general tab of the project to be dialed is the setting to allow this; a dropdown labeled Outbound ANI/CLI:




Voice Channels, and Play Notification Beep to agent

On the predictive tab is the Maximum Number of Voice Channels to be used and the Play notification beep to agent setting, check so that agents hear a short beep when they connect to a predictive call. The Maximum Number of Voice Channels should be set to 2 times the number of agents logged in. Number of Retry should be set to 10




(Note: The number of times a callback contact record is called is based on specific campaign requirements this suggested value is a typical setting used by most users)



Ringtime and tone detection


The ringtime setting on the regulations tab specifies how long, in seconds, the system will let a call ring before determining it as no answer, for Business to Consumer dialing, 30 seconds of ringtime is optimal,

From the Tone Detection drop-down list, select how long CCA waits (in seconds) to determine whether the call was answered by a person or an answering machine. (CCA determines this by running an algorithm.) For Business to Consumer dialing 1.1 seconds is optimal



Maximum Dropped Call Rate and Aggressivity Factors

Type the maximum percentage of dropped predictive calls to allow in the Maximum Dropped Call Rate field, this should be set to 3.0, and the agent Aggressivity factor should be set to 0.75 and the pool size set to 1, and the Sampling size should be set to 500



Actions

For each condition (If Busy, If No Answer, and so on) select an action for CCA to take. (Notice that new fields appear after making a selection.)

Actions: If Answering Machine -> Route to project




(Note: This provides flexibility to leave messages, play an IVR or any other call treatments based on specific campaign needs)

Actions: Answer -> Connect Agent.

If no agent available -> Route to project



(Note: This provides flexibility to leave messages, play an IVR or any other call treatments based on specific campaign needs)




Chapter 3: Dialer Lists

The dialer list is the data that will be used by the system to make outbound calls. The dialer list must meet the following criteria:

- CSV format
- A column for country code
- A column for phone numbers
- A column for company
- A column for project

To upload a dialer list


- 1. On the Options side menu, click Projects and then navigate to the desired project.
- 2. Once in the desired project, click the Dialer Lists tab.
- 3. Click the Plus sign:



The **Select Pattern Matching Field CAUTION** will overwrite the data contained within the column selected. The column selected for pattern matching data to be written should be non-numerical field such as Department.


The Add Dialer List window appears:





- 3. On the Add Dialer List window (above):
 - Type a name for the dialer list in the General field
 - Type a short description of the dialer list in the description field
 - Under Import New List, click Browse and then find the CSV file.
- Click Next.

The Map Fields to this Display Template screen appears.



5. Associate (map) the columns in the dialer list (csv file) with the fields in the contact template via the drop down menus




This association is the only way that Administration Manager can determine the data in the dialer list.

Notice that:




- The gray fields are from the contact template that the project uses.
- The fields in the list boxes are from the columns in the dialer list.
- 6. Click Next



- 7. Click Upload.
- 8. After the dialer list finishes uploading, click Close window.

The CSV file appears in the Dialer List tab.



Click Apply. The Dialer List upload is complete when the new list appears on the above Dialer List tab.

Time Zones

When starting a predictive project manually, Oracle Contact Center Anywhere tries to dial all numbers in the project's dialer lists. To dial only the selected numbers, **time zones** or to make calls at specific times, you must create a Start/Stop Schedule. Before starting or scheduling a predictive project, ensure that the specified conditions are met within Administration Manager and CCA Reports:

Administration manager

- 1. From the Navigation pane, click Libraries, **Matching Patterns**. Do one of the following:
- 2. Click **Add** and the Matching Patterns screen opens.
- 3. Complete the Matching Patterns screen, and click OK.
 - a. The following table describes the fields.


Field	Description
Name	Type a name that identifies the purpose of this pattern.
Pattern	Type a string pattern. The suggested string pattern for time zones is the first letter of the time zone. For example, type in the letter C to represent the central time zone.
Description	Type a description for this pattern to help identify it quickly in your Matching Patterns library.

- 4. Repeat Step 3 of this procedure until all the matching patterns that your contact center requires are created. Click OK
- 5. From the Navigation pane, click Libraries, Pattern Matching Groups.
- 6. Click Add and the Pattern Matching Groups screen opens.
 - a. The following table describes the fields.

Field	Description
Name	Type a name for this Pattern Matching Group.
Description	Type a description for this Pattern Matching Group to help identify it quickly in your library.
Select the prefix patterns for this Group	Select the Matching Patterns to include in this group.

7. Repeat Step 6 of this procedure until all the Pattern Matching Groups required for your contact center are created. Then Click OK.

- 8. Within the project, that contains the list you wish to dial,
 - a. click on the Predictive tab and
 - b. click on the Start/Stop Schedule sub tab
 - c. click on the **Scheduled Start/Stop** radio button
 - d. click the Add icon and the Weekly Predictive Schedule window appears







- e. Type in a name for the predictive schedule in the name field
- f. Select **Use Contact Customized field for Matching**, and select the desired time zone's Pattern Group.
- g. From the **Days** drop-down list, select the days that the predictive dialing schedule runs (such as Monday through Friday).
- h. From the **Daily Hours** drop-down list, select when the predictive dialing schedule runs (such as 8:00 A.M to 5:00 P.M.).
- i. From the **Time Zone** drop-down list, select where the project runs.
- i. Click OK to save the schedule.
- k. In the Predictive tab, click OK.

CCA Reports

After entering the Start/Stop schedule in the Administration Manager, the dialer list will need to be scrubbed against the Pattern Match Area Code within **CCA Reports.**

- 1. Sign in to CCA Reports
- 2. Click on Predictive List Maintenance
- 3. Under Select Action Type; click the **Pattern match Area Code** radio button.





- 4. Within the **Project** selection area, select the desired project.
- 5. With the **Predictive List** selection area select the desired project.
- 6. Click Update Contacts

List Activation

There are two steps to activating a list; first the Project needs to be started. To do this log into the Administration Manager, go to Projects→ your project name→ and then Predictive. Select Start/Stop. Select the start type for the project either Manual or Schedules mode and then click on the Start button. You will see the start progress indicator cycling back and forth, click the Apply button, the Project is now started.


Take note that the list of authorized Supervisors is selected in the Permissions tab. The next step will require the Supervisor to activate a list and they will only be able to do so if the Administrator has authorized them in the Permissions tab.

Be sure that the Permission is done before the Supervisor logs in.




(Note: After the Administrator has given this authorization to the Supervisor, if the Supervisor was already logged in, they should log off, close the CCA window close their browser. Open a new browser and log back in)

The second step to List Activation is done in the Supervisors screen. The Supervisor should navigate to the Outbound Control Tab.



The supervisor will then need to expand out the Project name they wish to activate and then to check off the list to dial.



Contact and Support Information

Promero, Inc.

1100 Park Central Blvd South, Suite 2500

Pompano, FL 33064

Tel: (954) 935-8800 **Fax:** (954) 935-8842

SALES AND PRODUCT INFORMATION

E-mail: sales@promero.com Toll Free: (888) 204-0822 Tel: (954) 935-8800 Option 7

.

TECHNICAL SUPPORT

E-mail: Support@promero.com

Toll Free: (866) 570-7334

Tel: (954) 935-2380

Tel: (954)935-8800 Option 5